Подешавање аутентификације одлазне поште у OutlookExpress-u 6

30

Outlook Express 6

Изаберите Tools мени и опцију Account Settings Изаберите "Mail" tab. Изаберите свој mail.jotel.co.rs налог:

		2	
Al Mail New	s Directory Service	£	Add
Account	Туре	Connection	Remove
Connect wsu.edu	mail mail (default)	Any Available Local Area Network	Properties
S. 6			Set as Defau
			Import
			Export
			Set Order

Селектујте "Properties". Затим изаберите "Servers" tab. За "Outgoing Mail (SMTP)", укуцајте име сервера "mail.jotel.co.rs" и чекирајте опцију "My server requires authentication" како је приказано:

Server Information My incoming mail server is a POP3 server. Incoming mail (POP3): mail.jotel.co.rs Outgoing mail (SMTP): mail.jotel.co.rs Incoming Mail Server Account name: korisnicko_ime Password: V Remember password Log on using Secure Password Authentication Outgoing Mail Server V My server requires authentication Settings	100000	Canier	0	C	A REPORT OF	
Server Information My incoming mail server is a POP3 server. Incoming mail (POP3): mail.jotel.co.rs Outgoing mail (SMTP): mail.jotel.co.rs Incoming Mail Server Account name: korisnicko_ime Password: ••••••• © Remember password Log on using Secure Password Authentication Outgoing Mail Server © My server requires authentication Settings	eneral	Servers	Connection	Security	Advanced	
My incoming mail server is a POP3 server. Incoming mail (POP3): mail.jotel.co.rs Outgoing mail (SMTP): mail.jotel.co.rs Incoming Mail Server Account name: korisnicko_ime Password: •••••• © Remember password Log on using Secure Password Authentication Outgoing Mail Server © My server requires authentication Settings	Server	Information	1			
Incoming mail (POP3): mail.jotel.co.rs Outgoing mail (SMTP): mail.jotel.co.rs Incoming Mail Server Account name: korisnicko_ime Password: V Remember password Log on using Secure Password Authentication Outgoing Mail Server V My server requires authentication Settings	My in	ncoming m	ail server is a	POP3	server.	
Outgoing mail (SMTP): mail.jotel.co.rs Incoming Mail Server Account name: korisnicko_ime Password: V Remember password Log on using Secure Password Authentication Outgoing Mail Server V My server requires authentication Settings	Incoming mail (POP3):		POP3): m	mail.jotel.co.rs		
Incoming Mail Server Account name: korisnicko_ime Password: •••••• © Remember password Log on using Secure Password Authentication Outgoing Mail Server © My server requires authentication Settings	Outg	oing mail (SMTP): m	ail.jotel.co	D. rs	
Account name: korisnicko_ime Password: Password: Remember password Log on using Secure Password Authentication Outgoing Mail Server V My server requires authentication Settings	Incomir	ng Mail Ser	ver	Le.	8	
Password:	Account name:		ko	korisnicko_ime		
Remember password Log on using Secure Password Authentication Outgoing Mail Server My server requires authentication Settings	Pass	word:	•••			
Log on using Secure Password Authentication Outgoing Mail Server My server requires authentication Settings			₩ F	Remember	password	
Outgoing Mail Server		og on usin	g Secure Pas	sword Auth	entication	
My server requires authentication Settings	Outgoir	ng Mail Ser	ver			
	V N	ly server n	quires auther	tication	Setti	ngs
		tracowersk				

Сада изаберите "Settings" дугме.

Изаберите опцију "Log on Using" и унесите своје корисничко име и лозинку а затим кликните на "OK" дугме.



Изаберите "Advanced" tab.

Под Server Port Numbers, испод Outgoing Mail (SMTP) поља, чекирајте "**This server requires a** secure connection (SSL)" и промените сервер број на **465**.

Изаберите "ОК" дугме да снимите све промене.